

Legitronic Labeling Software Number Serialization

This paper will help you get started using basic number serialization in Legitronic Labeling Software. If you need additional support, the Help screens will guide you.

1. Create a Text Field. (Figure 1)



2. Right click in the Text Box and choose Serial. (Figure 2)



Figure 2

- 3. Click the Yes button for Serial Number. (Figure 3)
- 4. Add the Start Value. (Figure 3)
- 5. Choose the amount to Increment. (Figure 3)
- 6. Click Apply. (Figure 3)

Note: The highlighted entries show options you can use if you choose.



Figure 3

<u>NOTE:</u> Use steps 7 - 9 only if you are using a True Type Font or serializing a number other than in the rightmost places.

7. Click File > Printer Setup. (figure 4)



- 8. Set Computer or printer repetition to Computer Repetition. (Figure 5)
- 9. Click OK. (Figure 5)

Weber Zebra 105SL 300 Properties ? × Device Settings		
 Weber Zebra 105SL 300 Device Settings Darkness: <u>Send the darkness command</u> Setup Darkness Speed: <u>Send the speed command</u> Setup Speed: <u>2 inches/second</u> Label top adjustment: <u>Send the label top command</u> Setup Label top Font Cache: <u>Use the printer's default font cache</u> Setup Font Cache: <u>1 kilobytes</u> Setup label rotation: <u>No label rotation</u> Computer or printer repetition: Printer repetitior 		
Print mode: <u>Tear off adjustment</u> Printer repetition Media tracking: <u>Die cut</u> Computer repetition		

Figure 5

10. Save and close your label. (Figure 6)



11. Open the label for printing. (Figure 7)

	Legitronic Labeling Settware 3.6.2 Edit Vive For Tools Window Help CEL A SI FITTUE ET V A SEC SEC A SI for Printing CLASSING SET
ok in:	🚔 My Documents 💽 🔶 🖆 📰 🗸
	Alien Academ BioFormTest2.lbl Legi362 Mine Mine Migeneric.lbl Miny Data Sources ALabel1.lbl My Downloads My Labela
ents	My Pictures My Projects My Quotes
ter	My Shapes
rk	WinZip v7.0
	File name: Open
	Files of type: Label Files (*.lbl)

Figure 7

- 12. Enter the number of serialized labels to print. (Figure 8)13. Click Save to disk. (Figure 8)14. Click Print. (Figure 8)

Legitronic Labeling Sof	tware 3.6.2 - L <mark>- 🗆 ×</mark> Vindow Help		
	[[· · · · · · · · · · · · · · · · · ·		
	AMENDEØØ		
ELabel1.lbl			
Job Settings Ports			
Print <u>J</u> ob			
Label Stock:			
I Submit Job Suspended	C Send Template		
🗖 🔲 🛄 🔲 🗌	C Send Variable Data		
Auto Repeat	Preview		
Disable Auto Print Submit inb ASAP	None First abel		
Store 5300 Print Job	C Every Label		
Print Count			
Number of Identical Labels	Auto Counts:		
Number of Serial Labels 🔺 🔔	Lite gato serial field		
1000	Multiple Across:		
Cut / Pause Count	C Horizontal serialization		
	○ Vertical serialization		
Print Cancer	<u>Save to disk</u> Help		
For Help, press F1	(x=3.087, y //		

Figure 8